## Labcorp Oklahoma, Inc. Test Directory

## **Bone Marrow Evaluation**

Order Name: Bone Marrow
Test Number: 2917900
Revision Date: 11/16/2023

TEST NAME	METHODOLOGY	LOINC CODE
Complete Blood Count (CBC) with Automated Differential	Flow cytometry	See Indvidual Assays
Reticulocyte (Retic) Count	Flow cytometry	
Immature Platelet Fraction	Flow cytometry	71693-6
Hemo Bone Marrow		
JIC Clot		
JIC Lavender		

Service provided by Labcorp Oklahoma, Inc. All Rights Reserved. © 2003 - 2025

## Labcorp Oklahoma, Inc. Test Directory

pecimen	Specimen Volume (min)	Specimen Type	Specimen Container	Transport Environment	
referred	See Instructions	See Instructions	See Instructions	See Instructions	
Instructions	Aspirate - Smears				
	1. Place 2 mL of aspirate into a 2.7 mL light blue Sodium Citrate (3%) tube and mix thoroughly. Heparin or EDTA anticoagulants should NOT be us				
	since they may produce staining artifacts.				
	2. Prepare 8-10 pull prep slides from the anticoagulated aspirate. Send the remaining citrated aspirate to the laboratory. Alternatively, send the ent				
	citrated aspirate to the lab ASAP for preparation of smears.				
	Aspirate – Additional testing (Flow Cytometry, Cytogenetics, Chromosomes, PCR & Microbiology)				
	1. Place at least 2-3 ml of aspirate into each of the following tubes for additional testing:				
	- One Lavender EDTA tube for Flow Cytometry and Molecular testing.				
	- One Dark green sodium heparin, no gel tube for Chromosome studies.				
	- If cultures have been requested on the bone marrow, also add 2 mL of aspirate into a Yellow SPS tube or Wampole Isolator tube.				
	2. Invert the tubes several times to allow for proper specimen and anticoagulant mixing.				
	3. Pre-authorization for cytogenetic and molecular testing should be obtained. Include a signed Advanced Beneficiary Notice with this testing requi				
	Clot (for Histology Sections)				
	1. Allow remaining aspirate to clot in syringe. Slowly remove plunger and clot from syringe.				
	2. Place clot in a sterile screw top cup containing 10% buffered formalin. Use enough formalin to cover the specimen.				
	Bone Biopsy and Touch Preparations				
	1. If an aspirate has been obtained, place the core biopsy in a sterile cup and cover with 10% buffered formalin.				
	2. If there is a dry tap and the physician obtains only a core biopsy, a generous biopsy or several smaller biopsies should be obtained to allow complete testing.				
	A. Touch preparations should be made using the biopsy, removing as much blood as possible prior to making touch preps. Prepare 6-8				
	touch prep slides by touching, not pressing, the biopsy to clean slides. Make sure slides are properly labeled with the patient name and				
	DOB, in pencil.				
	B. The core biopsy specimen(s) should then be divided or sectioned for additional testing (e.g. Flow and/or Chromosomes), and separate				
	pieces should be placed into the following:				
	- One Piece in a sterile cup, covered in 10% formalin for histology				
	- One Piece in a sterile cup, covered in RPMI for Flow				
	- One Piece in RPMI for Cytogenetics				

Each Bone Marrow order should be accompanied by a current history and physical. In addition to filling out the **Hematopathology Work-Up Requisition**, please use the **Bone Marrow collection form as a checklist** to document the specimens collected and submitted to the laboratory.

Please fill out this form and submit it alongside your specimens. Those forms and a helpful **Bone Marrow Collection Quick Reference Visual Guide and other documents** can be found at the following links.

Bone Marrow Collection Quick Reference Visual Guide

Bone Marrow Collection Form

Hematopathology Work-up Requisition

GENERAL INFORMATION	
Clinical Use	Pathology Report will be issued on this Component and Result Alias at an additional charge on Order/Result Code: [8411010] Hematology Consult  Addenum Pathology Reports will be issued on this Component and Result Alias at an additional charge on Order/Result Code: [8070150] Addendum Report
Notes	A bone marrow evaluation includes examination of the peripheral blood smear, a CBC with automated differential, immature platelet fraction and a reticulocyte count. In addition to the bone marrow specimens, send an EDTA whole blood specimen for this testing. All specimens should be properly labeled with the patient name, MRN, DOB, collection date and time and the specimen types (aspirate, biopsy, clot or blood).
CPT Code(s)	85025, 85045, 85055 (additional codes are possible depending on clinical findings)
Lab Section	Hematology

Service provided by Labcorp Oklahoma, Inc. All Rights Reserved. © 2003 - 2025 Labcorp Oklahoma, Inc. Test Directory